

??ADSL/PPPoE?? ??IP?????

```
# [ ] ADSL/PPPoE [ ] Dialer [ ] 206.82.0.0/16 [ ]
## [ ]
ADSL [ ] `Dialer1` [ ] **`in` [ ] ** [ ] ** [ ] ACL [ ]
100~199 [ ] ** [ ] `206.82.0.0/16` [ ]

### [ ]
`206.82.0.0/16` [ ] `255.255.0.0` → [ ] `0.0.255.255`

## [ ] Dialer1 [ ]
```ios
conf t
! 1. [] ACL [] 206.82.0.0/16 []
access-list 160 deny ip 206.82.0.0 0.0.255.255 any log
! [] ACL [] deny any [] permit ip any any []
access-list 160 permit ip any any

! 2. [] ADSL [] Dialer1 [] in []
interface Dialer1
 ip access-group 160 in
exit
end
...

[]
[] 1 [] 206.82.0.0/16 []
- [] `206.82.x.x` [] TCP/UDP []
- [] `206.82.x.x` []

[] 2 [] 206.82.0.0/16 []
[] Dialer1 [] out []
```ios
conf t
access-list 160 deny ip any 206.82.0.0 0.0.255.255 log
interface Dialer1
 ip access-group 160 out
end
...

## [ ] ACL150 [ ] ACL [ ]
[ ] `access-list 150` [ ] ACL [ ] ACL [ ]
deny [ ] permit [ ]
```

```

```ios
conf t
! [] ACL[]
access-list 150 deny ip 206.82.0.0 0.0.255.255 any log
! []
access-list 150 permit udp any host 218.1.210.220 range 16000 20000
access-list 150 deny udp any host 218.1.210.220 eq 5060
access-list 150 permit ip any any
! [] Dialer1 in[]
end
```

```

```

## [ ]
1. [ ] ACL[ ] 206.82[ ]
```ios

```

```

show access-list 160
show access-list 150
```

```

```

2. [ ] Dialer[ ] ACL[ ]
```ios

```

```

show run interface Dialer1
```

```

```

3. [ ] `log` [ ]
```ios

```

```

terminal monitor
```

```

```

4. [ ] ACL[ ]
```ios

```

```

clear access-list counters 160
```

```

```

## [ ]

```

```

1. *[ ] *[ ] `ip access-group XXX in` [ ] out
[ ]

```

```

2. ACL[ ] deny[ ] permit[ ] *[ ] **
[ ]

```

```

3. `log` [ ] IP[ ]

```

```

4. ADSL[ ] Dialer1[ ] ATM/[ ] ACL[ ] Dialer
[ ]

```

Revision #1

Created 17 June 2026 09:38:05 by Admin

Updated 17 June 2026 09:38:37 by Admin