

????????????????????IP??

配置 Cisco 3945 配置 NAT (192.168.0.5 → 122.144.131.26) 配置 122.144.131.26

配置

- IP 192.168.0.5
- 389

配置

- 44389
- IP 122.144.131.26

????

1. ?? ACL?????? IP

```
ip access-list extended LDAP-ACCESS
permit tcp host 122.144.131.26 any eq 44389
deny ip any any
```

配置

- IP 122.144.131.26 44389
-

2. ?? NAT ????????

配置 GigabitEthernet0/0 IP X.X.X.X

```
ip nat inside source static tcp 192.168.0.5 389 interface GigabitEthernet0/0 44389
```

配置

- X.X.X.X:44389 192.168.0.5:389

3. ????? ACL

????????

GigabitEthernet0/0 ?????

ACL?

```
interface GigabitEthernet0/0
 ip access-group LDAP-ACCESS in
```

?????

????????

```
ip access-list extended LDAP-ACCESS
 permit tcp host 122.144.131.26 any eq 44389
 deny ip any any

interface GigabitEthernet0/0
 ip address X.X.X.X 255.255.255.0
 ip nat outside
 ip access-group LDAP-ACCESS in

interface GigabitEthernet0/1
 ip address 192.168.0.1 255.255.255.0
 ip nat inside

ip nat inside source static tcp 192.168.0.5 389 interface GigabitEthernet0/0 44389
```

??


1. ???? IP ??

```
telnet X.X.X.X 44389
```

??????

2. ???? IP ?????



389/44389 

Revision #1

Created 23 September 2025 09:44:24 by Admin

Updated 23 September 2025 09:44:55 by Admin