


```
grdctl rdp set-tls-cert ~/.local/share/gnome-remote-desktop/rdp-tls-cert.pem grdctl rdp set-t
```

??????????

```
grdctl status --show-credentials
```

??????????

```
Overall:      Unit status: active RDP:      Status: enabled      Port: 3389      TLS certificate:
```

???

???????? 3389 ?????????????? RDP????? **0x904?**

?????????

```
journalctl --user -u gnome-remote-desktop.service --since "1 min ago"
```

????????

```
gnome-remote-desktop-daemon: ../src/libei-connection.c:75: ei_connection_get_context: Asserti
```

???? ?? **gnome-remote-desktop 49.0 ??? bug?** ? RDP ??????????libei
??

????????????????????**view-only** **libei?** ?????????????????? view-only?????????????????
RDP ?????????? Ubuntu ??? **??????**

????


????????????????????????????????????? view-only ?????????? view-only??? 3389
?????????????????????????????????????

```
???? ? ?? view-only????????????? ? ????? RDP?view-only ?????? libei bug? ? ????? ? ??  
view-only?libei ?????????????? ? ?????????????? ? ????? ? ????? ? ????? ? ??????
```

????????????????????

??????????????????????~

????????????????



Revision #1

Created 28 May 2026 01:00:48 by Admin

Updated 28 May 2026 01:01:38 by Admin